



## Quick search



Docs » 1 TALOS Software manual

- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

# 1 TALOS Software manual

Thank you for choosing PAL Robotics. This User Manual contains information related to the TALOS robot developed by PAL Robotics. Every effort has been made to ensure the accuracy of this document. All the instructions must be strictly followed for proper product usage. The software and hardware described in this document may be used or replicated only in accordance with the terms of the license pertaining to the software or hardware. Reproduction, publication, or duplication of this manual, or any part of it, in any manner, physical, electronic or photographic, is prohibited without the explicit written permission of PAL Robotics.

## 1.1 GENERAL INFORMATION

This User Manual is intended to be used as an index for the user, to access the most common topics and usages of the TALOS robot. It doesn't pretend to substitute or override the documentation presented in the handbook or other manuals.

## 2 PAL repositories

The following table contains a brief description of the packages available at the [GitLab](#) repository.



## Quick search



### 1 TALOS Software manual

#### 1.1 GENERAL INFORMATION

#### 2 PAL repositories

#### 3 Gazebo simulation

#### 4 PAL Physics simulator

##### 4.1 Simulation with ideal actuation

##### 4.2 Simulation with gaussian noise

#### 5 Initialization script

#### 6 Position controllers

##### 6.1 Controller manager

##### 6.2 Default controllers

##### 6.3 Full body position controllers

##### 6.4 Play motion

#### 7 Walking controller

##### 7.1 Walking offsets calibration

###### 7.1.1 Load controller

###### 7.1.2 Start calibration

###### 7.1.3 Save the results

#### 8 Torque offset calibration

#### 9 Torque control

##### 9.1 Joint Torque control

##### 9.2 The DCM controller

#### 10 Walking torque control

#### 11 PAL Whole Body Control

##### 11.1 Kinematic WBC

##### 11.2 Dynamic WBC

##### 11.3 WBC grasp demo

#### 12 Introspection controller

#### 13 Validation post upgrade

##### 13.1 WebCommander

##### 13.2 Position Control

##### 13.3 Walking Controller

##### 13.4 Whole Body control

##### 13.5 Torque Offset Calibration

##### 13.6 Torque Control

##### 13.7 Walking Torque Control

Group containing repositories of materials, examples and other useful packages for TALOS customers.

Package name	Shared projects	Archived projects	Search by name	Last created
talos_X_specifics				1 week ago
talos_X_specifics				1 week ago
talos_X_specifics				1 week ago
pal_kv				1 week ago
imu_comparison_controller				1 week ago
talos_X_specifics				1 week ago
talos_X_specifics				1 week ago
smach_c				1 week ago
rubber_stamping_demo				1 week ago
rt_loss_detector				1 week ago
talos_X_specifics				1 week ago
talos_X_specifics				1 week ago

Package name	Description
talos_X_specifics	Specific parameters for TALOS X
pal_kv	KVH Imu driver by PAL
imu_comparison_controller	Tool to compare two IMUS (ex. KVH vs Orientus)
smach_c	Integration of ROS smach in C++ to write state machines
rubber_stamping_demo	WBC Kinematic demo of the robot stamping
rt_loss_detector	Tool to check if code is real



## Quick search



1 TALOS Software manual

1.1 GENERAL INFORMATION

2 PAL repositories

3 Gazebo simulation

4 PAL Physics simulator

4.1 Simulation with ideal actuation

4.2 Simulation with gaussian noise

5 Initialization script

6 Position controllers

6.1 Controller manager

6.2 Default controllers

6.3 Full body position controllers

6.4 Play motion

7 Walking controller

7.1 Walking offsets calibration

7.1.1 Load controller

7.1.2 Start calibration

7.1.3 Save the results

8 Torque offset calibration

9 Torque control

9.1 Joint Torque control

9.2 The DCM controller

10 Walking torque control

11 PAL Whole Body Control

11.1 Kinematic WBC

11.2 Dynamic WBC

11.3 WBC grasp demo

12 Introspection controller

13 Validation post upgrade

13.1 WebCommander

13.2 Position Control

13.3 Walking Controller

13.4 Whole Body control

13.5 Torque Offset Calibration

13.6 Torque Control

13.7 Walking Torque Control

	time safe
talos_wbc	Kinematic WBC Parameters + launch files + documentation
talos_pal_physics_simulator	PAL physics simulator parameters + documentation
talos_robot	URDF description + robot parameters
pal_deployer_cfg	Deployer parameters (ex. zero offsets)
pal_locomotion_actions	DCM controller actions + documentation
talos_pal_locomotion	DCM controller parameters + Dynamic WBC stack + documentation



## Quick search



1 TALOS Software manual

1.1 GENERAL INFORMATION

2 PAL repositories

3 Gazebo simulation

4 PAL Physics simulator

4.1 Simulation with ideal actuation

4.2 Simulation with gaussian noise

5 Initialization script

6 Position controllers

6.1 Controller manager

6.2 Default controllers

6.3 Full body position controllers

6.4 Play motion

7 Walking controller

7.1 Walking offsets calibration

7.1.1 Load controller

7.1.2 Start calibration

7.1.3 Save the results

8 Torque offset calibration

9 Torque control

9.1 Joint Torque control

9.2 The DCM controller

10 Walking torque control

11 PAL Whole Body Control

11.1 Kinematic WBC

11.2 Dynamic WBC

11.3 WBC grasp demo

12 Introspection controller

13 Validation post upgrade

13.1 WebCommander

13.2 Position Control

13.3 Walking Controller

13.4 Whole Body control

13.5 Torque Offset Calibration

13.6 Torque Control

13.7 Walking Torque Control

<a href="#">pal_wbc_utils</a>	Examples + documentation for Kinematic WBC
<a href="#">pal_walking_tutorials</a>	Examples + documentation for walking in position
<a href="#">pal_optimization_nl_tutorials</a>	Examples + documentation for PAL optimization
<a href="#">pal_locomotion_tutorials</a>	Examples + documentation for walking in torque control
<a href="#">wbc_grasp_demo</a>	WBC Kinematic / Dynamic demo of the robot grasping
<a href="#">pal_base_ros_controller_tutorials</a>	Examples + documentation of PAL ROS control wrapper
<a href="#">talos_uat_tests</a>	UAT tests to validate the robot after an



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
- 6.1 Controller manager
- 6.2 Default controllers
- 6.3 Full body position controllers
- 6.4 Play motion
- 7 Walking controller
- 7.1 Walking offsets calibration
- 7.1.1 Load controller
- 7.1.2 Start calibration
- 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
- 9.1 Joint Torque control
- 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
- 11.1 Kinematic WBC
- 11.2 Dynamic WBC
- 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
- 13.1 WebCommander
- 13.2 Position Control
- 13.3 Walking Controller
- 13.4 Whole Body control
- 13.5 Torque Offset Calibration
- 13.6 Torque Control
- 13.7 Walking Torque Control

TALOS Handbook

upgrade

TALOS Latest Handbook

### Note


It is recommended to read carefully the **README's** of the above packages to better understand the PAL software architecture.

## 3 Gazebo simulation

Gazebo is an open-source 3D robotics simulator.

To start TALOS using the Gazebo simulator run:

```
roslaunch talos_gazebo talos_gazebo.launch
```



By default it loads the *empty\_world*. It is possible to load other environments described in the **pal\_gazebo\_worlds** package.

```
roslaunch talos_gazebo talos_gazebo.launch
```

```
world:=small_office
```

Gazebo tries to replicate through plugins the same behaviour and interface that the one in the real robot. This means that all control applications will be embedded and executed inside the simulation. To



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

```
roslaunch talos_gazebo talos_gazebo.launch debug:=true
```

The *default controllers* needs to be launched as follows in Gazebo.


```
roslaunch talos_controller_configuration_gazebo
default_controllers.launch
```

### Warning

Before deploying and executing any kind of software in the robot, it is mandatory to validate it in simulation.

## 4 PAL Physics simulator

The PAL Physics simulator is a custom simulator implemented by PAL Robotics that emulates more realistic physics than Gazebo. It is meant to be used as the main simulator when developing applications in Torque control.



It is possible to start the simulation with two different profiles:

1. Ideal actuators
2. Gaussian noise in the actuators

The **README** of the [talos\\_pal\\_physics\\_simulator](#) contains a deeper explanation on how to:



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

- Load a simulated environment.
- Interact with the robot applying an external force.
- How to launch the controllers in each simulator profile.
- Understand the different robot model available.
- How to start the simulation using *GDB* or *Valgrind*.

## 4.1 Simulation with ideal actuation

This simulates ideal actuators with **zero noise**. The physics are quite similar to the ones of Gazebo.

```
roslaunch talos_pal_physics_simulator
talos_pal_physics_simulator.launch
```

Start torque control (*Direct torque control*):

```
roslaunch talos_pal_locomotion
talos_dcm_walking_controller.launch
```

## 4.2 Simulation with gaussian noise

This simulates ideal actuators with **Gaussian noise**. The physics are quite close to the real robot.

```
roslaunch talos_pal_physics_simulator
talos_pal_physics_simulator_with_actuators.launch
```

Start torque control using (*Inertia shapping effort torque control*):

```
roslaunch talos_pal_locomotion
robot_dcm_walking_controller.launch simulation:=true
```

### Warning



## Quick search

- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

Any new application in torque control should be previously tested and validated in the PAL physics simulator with Gaussian noise.

## 5 Initialization script

The initialization script is used for safety to check that the readings from all sensors are valid.

### Note

It should be triggered before starting any controller with the robot hanging in air. Wait until the robots says that initialization has finished successfully.

It can be triggered from the WebCommander (Tab Controllers) or from the terminal:

```
roslaunch talos_controller_configuration
talos_initialisation.py --yes
```

The script:

- Puts the robot in the default position
- Check that the torques are correct (under 5 N/m deviation)
- Reset the 6 axis F/T sensors of the feet.

For more information check the handbook section.

### Warning

If the initialization script fails, check in the logs for the cause. If the reason is a torque sensor deviation, please run the torque offset calibration again.





## Quick search

- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

# 6 Position controllers

Talos uses ROS control as a control interface. It has integrated the default **JointTrajectoryControllers** as well as **Movelt!** for planning.

The available JointTrajectoryControllers are:

- left\_arm\_controller
- right\_arm\_controller
- head\_controller
- torso\_controller
- left\_leg\_controller
- right\_leg\_controller
- left\_gripper\_controller
- right\_gripper\_controller

## 6.1 Controller manager

The controller manager interface allow us to:

- List loaded and / or running controllers

```
rosservice call /controller_manager/list_controllers
```

- Start or stop controllers

```
rosservice call /controller_manager/switch_controllers
```

- Load a controller if the parameters are loaded in the specific namespace

```
rosservice call /controller_manager/load_controller
```

- Unload a controller



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
- 6.1 Controller manager
- 6.2 Default controllers
- 6.3 Full body position controllers
- 6.4 Play motion
- 7 Walking controller
- 7.1 Walking offsets calibration
- 7.1.1 Load controller
- 7.1.2 Start calibration
- 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
- 9.1 Joint Torque control
- 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
- 11.1 Kinematic WBC
- 11.2 Dynamic WBC
- 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
- 13.1 WebCommander
- 13.2 Position Control
- 13.3 Walking Controller
- 13.4 Whole Body control
- 13.5 Torque Offset Calibration
- 13.6 Torque Control
- 13.7 Walking Torque Control

```
rosservice call /controller_manager/unload_controller
```

## 6.2 Default controllers

The default controllers include all the **upperbody JointTrajectory controllers** and the **walking controller**. It allows to run any kind of motion that doesn't include the legs as a resource.

```
roslaunch talos_controller_configuration
default_controllers.launch
```

In Gazebo:

```
roslaunch talos_controller_configuration_gazebo
default_controllers.launch
```

Check the walking section in the handbook to see how to make the robot walk.

## 6.3 Full body position controllers

To start all the **JointTrajectory** controllers run:

```
roslaunch talos_controller_configuration
position_controllers.launch
```

## 6.4 Play motion

Those controllers allow to send trajectories in joint space as predefined motions.

```
roslaunch play_motion run_motion NAME_OF_THE_MOTION
```

Or using the GUI:

```
roslaunch actionlib axclient.py /play_motion
```

**Note**



## Quick search



1 TALOS Software manual

1.1 GENERAL INFORMATION

2 PAL repositories

3 Gazebo simulation

4 PAL Physics simulator

4.1 Simulation with ideal actuation

4.2 Simulation with gaussian noise

5 Initialization script

6 Position controllers

6.1 Controller manager

6.2 Default controllers

6.3 Full body position controllers

6.4 Play motion

7 Walking controller

7.1 Walking offsets calibration

7.1.1 Load controller

7.1.2 Start calibration

7.1.3 Save the results

8 Torque offset calibration

9 Torque control

9.1 Joint Torque control

9.2 The DCM controller

10 Walking torque control

11 PAL Whole Body Control

11.1 Kinematic WBC

11.2 Dynamic WBC

11.3 WBC grasp demo

12 Introspection controller

13 Validation post upgrade

13.1 WebCommander

13.2 Position Control

13.3 Walking Controller

13.4 Whole Body control

13.5 Torque Offset Calibration

13.6 Torque Control

13.7 Walking Torque Control

For the motions of the legs, the argument *skip\_planning* needs to be set to True. Always validate in simulation first.

## 7 Walking controller

The walking controller is a ROS controller developed at PAL to make the robot walk in position using the **ZMP** based algorithm.

The controller is launched in the default controllers.

```
roslaunch talos_controller_configuration
default_controllers.launch
```

Z default kontrolerji

In the Gazebo simulator the command is different.

```
roslaunch talos_controller_configuration_gazebo
default_controllers.launch
```

Once the controller is started there are different ways to make the robot goal:

- Using the joystick **R1 + analog button**.
- Publishing in the topic `/walking_controller/cmd_vel`
- Using the service `/walking_controller/do_step` to perform a single step. The distances in the message are related to the stance foot.
- Using the service `/walking_controller/walk_steps` to perform n steps forward or backward.

For more information, check the documentation in the section walking controller of the handbook or check the examples in [pal\\_walking\\_tutorials](#)

### 7.1 Walking offsets calibration

Baje so iz Pala Kristini rekl



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

The walking controller uses offsets for each legs joints in order to have an even force distribution between both legs during the double support. The

`init_offset_controller` allow for tuning the walking offsets for the legs joints. This procedure is requested for achieving a better walk. The controller uses the information provided by the force and torque sensors of the ankles for moving slightly the legs joints in order to reduce the weight difference between the two feets and for reducing as much as possible the torques along axis y and z of every foot.

### 7.1.1 Load controller

The `init_offset_controller` is taking ownership of the lower body joints only, so

`joint_trajectory_controllers` are needed for the upper body. With the robot in the air, run the following commands:

```
roslaunch talos_controller_configuration
upper_body_position_controllers.launch

roslaunch talos_controller_configuration
init_offset_controller.launch

roslaunch play_motion run_motion walk_pose
```

### 7.1.2 Start calibration

Put the robot down and call the calibration service:

```
rosservice call /init_offset_controller/init_offsets
```

The robot will start moving slightly and after a while it will stop. In order to check if the calibration has succeeded you could run `pal-log deployer cat` and inspect the output file. The corrected offsets should be printed in the log file with the corresponding output measurements of the feet force torque sensors.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
- 6.1 Controller manager
- 6.2 Default controllers
- 6.3 Full body position controllers
- 6.4 Play motion
- 7 Walking controller
- 7.1 Walking offsets calibration
- 7.1.1 Load controller
- 7.1.2 Start calibration
- 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
- 9.1 Joint Torque control
- 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
- 11.1 Kinematic WBC
- 11.2 Dynamic WBC
- 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
- 13.1 WebCommander
- 13.2 Position Control
- 13.3 Walking Controller
- 13.4 Whole Body control
- 13.5 Torque Offset Calibration
- 13.6 Torque Control
- 13.7 Walking Torque Control

## 7.1.3 Save the results

```
roslaunch reemc_init_offset_controller offsets_saver
```

This will output a file `.pal/init_offset_controller/config/offsets.yaml`. This file should be copied in the folder ``.pal/talos_controller_configuration/config/`` and replace the `walking_specific_offsets.yaml` file. If this folder doesn't exist, create it with the following command:

```
configure_specifics.sh -c
talos_controller_configuration
```

Then copy the file:

```
cp .pal/init_offset_controller/config/offsets.yaml
.pal/talos_controller_configuration/config
/walking_specific_offsets.yaml
```

# 8 Torque offset calibration

To naj bi se ob redni uporabi

This procedure is meant to estimate the offsets of the torque sensors. During this proces the robot performs some movements to estimate the torque sensor offsets.

### Note

The robot needs to be on air and the position controllers as well as the dispatcher needs to be launched:

```
roslaunch talos_controller_configuration
position_controllers.launch
```

```
roslaunch trajectory_dispatcher
dispatcher_controller.launch
```



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

1. First perform the calibration movements. The argument type is used to specify leg or arm.

```
roslaunch pal_torque_offset_calibration_talos
pal_torque_offset_calibration.launch type:=leg
side:=both
```

2. Once finished the result can be seen here.

```
roslaunch pal_torque_offset_calibration_talos
compute_torque_offset_parameters.launch type:=leg
side:=both
```

Make a backup of the old params.

```
cp ~/.pal/talos_controller_configuration/config
/local_joint_control/actuator_parameters
/actuator_parameters_specific_params.yaml ~/.pal
/talos_controller_configuration/config
/local_joint_control/actuator_parameters
/actuator_parameters_specific_params.bkp
```

3. Reset the torque offsets with the last one computed.

```
roslaunch pal_torque_offset_calibration_talos
apply_torque_offsets.launch
```

### Warning

Compare the results with the previous offsets. If the standard deviation or some torque offset has a big difference with respect to the previous offsets don't start the DCM controller. Check how to validate torque control for a single joint in the Torque control documentation.

For more information check the torque offset calibration section in the handbook.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

# 9 Torque control

TALOS is equipped with a single axis joint torque sensor in every joint, except the wrists, grippers and head. This allows to control the robot in torque control.

## 9.1 Joint Torque control

The torque control is performed at joint level.

To validate that the torque control is behaving properly for a single joint, start the **sine sweep controller**.

```
roslaunch local_sine_sweep_torque_controller
sine_sweep_controller.launch
local_joint_control:=inertia_shaping_effort_analytic_dob_control
local_joint_control_pkg:=inertia_shaping_effort_control
joint_name:=leg_right_3_joint
controller_pkg_name:=talos_controller_configuration
```

### Note

The previous command starts torque control for the joint specified. In the case of the arms and the torso, the **local\_joint\_control** type is different.


### Warning

Before starting the controller the joint needs to be in zero gravity position, i.e the consequent links of the robot must be aligned with gravity. For example for the knee joint, the hip should be at 90° and the knee should also be at 90°.



## Quick search

- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control



### Note

If torque control is working fine the joint doesn't move from it's position, and when exciting manually in both directions, it should behave as a pendulum with almost no friction and no acceleration in any direction.

### Error

Please be cautious and always have the emergency stop during the process before validating torque control at joint level.

## 9.2 The DCM controller

The DCM is controller is the dynamic whole body controller implemented by PAL. This controllers uses





## Quick search




- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

as an input to the local torque control for each joint.

The default *WBC* stack, as well as the main parameters involved are defined in the [talos\\_pal\\_locomotion](#) package.

This controller contains a state machine internally where the user can push the desired walking actions. The walking actions available are:

- Balancing in double support (maintaining the DCM at the center of the support polygon)
- Balancing the DCM from one foot to the other
- Stand in one leg / Push down the leg
- Static walking (the DCM never goes out from the support polygon)
- Dynamic walking (**only validated in simulation**)
- Kinematic WBC wrapper (used for manipulation in dynamics ex. [wbc\\_grasp\\_demo](#))



To start the DCM controller in **Gazebo** or **PAL physics simulator** with ideal actuation.

```
roslaunch talos_pal_locomotion
talos_dcm_walking_controller.launch
```

To start the DCM controller in **PAL physics simulator** with noise.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch simulation:=true
```

To start the DCM controller on the **real robot**.

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch
```

To start the DCM controller with the **upper body controlled in position**.

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch
```

```
robot:=full_v2_fixed_upper_body
```

To start the DCM controller with **modified parameters** that overwrite the default ones.

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch
```

```
biped_parameters:=debris
```

For more information about:

- Safety in the DCM controller, or the parameters involved please check the [talos\\_pal\\_locomotion](#) package.
- Available actions, how to start / replace them, or how to implement a new action please check the [pal\\_locomotion\\_actions](#) package.
- Tutorials with examples on how to send steps to the robot, squat action, etc. please check the [pal\\_locomotion\\_tutorials](#) package.

## 10 Walking torque control

First start torque control on the robot with fixed upper body.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control


but the performance may not be as optimal as fixed upper body.

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch
```

```
robot:=full_v2_fixed_upper_body
```

Then open RViz with the *MarkerArray* (**/biped\_walking\_dcm\_controller/markers**) as shown in the picture.



### Warning

The **DCM / ICP actual (red)** and the **COP desired (blue)** should be close to the **DCM / ICP desired (green)**, otherwise the robot might fall after few steps.

### Warning

If the offset between the DCM / ICP actual and desired is big please run the torque offset calibration again.

### Note

If at any point the DCM goes out of the support polygon (orange rectangle) the controller will shut down because the robot is unstable.

- Using the static walk action.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

```
roslaunch pal_locomotion push_action.launch
action:=pal_locomotion::StaticWalkAction
```

### Controlling with the joystick.

```
roslaunch pal_locomotion relay
/walking_controller/cmd_vel
/biped_walking_dcm_controller/cmd_vel
```

Or sending predefined steps from a node of [pal\\_locomotion\\_tutorials](#).

```
roslaunch pal_locomotion_tutorials
static_steps_command
```

- Other option is to make the robot walk using the Stand one leg / Stand down leg actions. In this case, there is no need to start the static walk action.

```
roslaunch pal_locomotion_tutorials
static_steps_execution_node -d 2.0 -u 2.0 -s
5 -x 0.15 -y 0.1
```

### Note

To debug, after the torque offset calibration, or after change some parameters better use the previous node with  $x=0$  to ensure that the robot is able to do steps in place.

- To make the robot stand on one leg.

```
roslaunch pal_locomotion_actions
push_stand_one_leg_action -d 3.0 -u 3.0 -z
0.15 -s LEFT
```

To put the robot back in double support.

```
roslaunch pal_locomotion_actions
push_stand_down_leg_action -d 3.0 -u 3.0
```



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

Changing *LEFT* by *RIGHT* makes the robot stand on the other leg.

### Note

For debugging is also recommended to first stand the robot in one leg and put it down before start walking.

## 11 PAL Whole Body Control

The PAL Whole Body Control (WBC) is PAL's implementation of the **Stack of Tasks**. It includes a hierarchical quadratic solver able to accomplish different tasks with different priorities.

### 11.1 Kinematic WBC

To start the Kinematic simulation of the WBC in which all the joints are controlled in position.

```
roslaunch talos_wbc talos_wbc_standalone.launch
```

The previous command starts the simulator and the Whole Body Kinematic controller.

To start the controller standalone inside the robot or the simulator.

```
roslaunch talos_wbc talos_wbc.launch
```

For printing the list of active tasks / constrains in the stack.

```
rosservice call /whole_body_kinematic_controller
/get_stack_description
```



## Quick search



1	TALOS Software manual
1.1	GENERAL INFORMATION
2	PAL repositories
3	Gazebo simulation
4	PAL Physics simulator
4.1	Simulation with ideal actuation
4.2	Simulation with gaussian noise
5	Initialization script
6	Position controllers
6.1	Controller manager
6.2	Default controllers
6.3	Full body position controllers
6.4	Play motion
7	Walking controller
7.1	Walking offsets calibration
7.1.1	Load controller
7.1.2	Start calibration
7.1.3	Save the results
8	Torque offset calibration
9	Torque control
9.1	Joint Torque control
9.2	The DCM controller
10	Walking torque control
11	PAL Whole Body Control
11.1	Kinematic WBC
11.2	Dynamic WBC
11.3	WBC grasp demo
12	Introspection controller
13	Validation post upgrade
13.1	WebCommander
13.2	Position Control
13.3	Walking Controller
13.4	Whole Body control
13.5	Torque Offset Calibration
13.6	Torque Control
13.7	Walking Torque Control

To control both end effectors and the head of the robot using interactive markers execute.


```
roslaunch talos_wbc interactive_markers.launch
```

The previous command adds new tasks in the stack.

If the user want to control by topic the *source\_data* argument needs to be modified.

```
roslaunch talos_wbc interactive_markers.launch
```

```
source_data:=topic_reflexx_typeII
```



The **pal\_wbc\_utils** package contains:

- Brief explanation of the WBC and the default tasks loaded in the stack.
- Description of the available kinematic tasks.
- How to create a new task or constraint.
- How to create a specific stack.
- How to start or remove a task online.
- Code API and examples to push tasks online.
- Available references.

The **pal\_wbc\_tutorials** package explains how to create your own constraints. It contains an example on how to create a joint reference task.

The **talos\_wbc** contains:

- The available kinematic stacks.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

- The parameters involved in the Kinematic WBC.
- The available launch files to start the controller and push the different tasks.

## 11.2 Dynamic WBC

The Dynamic WBC is based on torque control. The inverse dynamic constraint is added (among other constraints) in the stack to produce the optimal torques that minimize the desired objective.

To start the dynamic torque control in simulation (without noise):

```
roslaunch talos_pal_locomotion
talos_dcm_walking_controller.launch
```

To start it on the real robot:

```
roslaunch talos_pal_locomotion
robot_dcm_walking_controller.launch
```

Once the DCM controller is started, push a wrapper of the Kinematic WBC in the state machine of the DCM controller.

```
roslaunch talos_pal_locomotion StartWBAction
```

Then is it possible to start the same demo of the `interactive_markers` or use any of the previous instructions by specifying the new namespace of the controller.

```
roslaunch talos_wbc interactive_markers.launch
ns:=/biped_walking_dcm_controller/wbc

rosservice call /biped_walking_dcm_controller
/wbc/get_stack_description
```

The `talos_pal_locomotion` package contains:



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

- The default dynamic stack loaded when starting the DCM controller.

- The WBC parameters related with the default dynamic stack.

The `talos_wbc` package contains:

- Examples of dynamics stacks.
- Standalone dynamic WBC demos.

### Warning

Except the `wbc_grasp` demo, the rest of dynamic WBC demos are not mature enough at this moment. Control both end effectors using the interactive markers may trigger safety preventions due to the discontinuities in torque.

## 11.3 WBC grasp demo

This `package` is devoted to exemplify how to command the robot to do tasks such as to approach a table, and to grasp and place an object on this table, by using WBC.

The demo is ready to be executed, either in Kinematic WBC or in Dynamic WBC, on the real robot as well as in simulation.





## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
- 4.1 Simulation with ideal actuation
- 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
- 6.1 Controller manager
- 6.2 Default controllers
- 6.3 Full body position controllers
- 6.4 Play motion
- 7 Walking controller
- 7.1 Walking offsets calibration
- 7.1.1 Load controller
- 7.1.2 Start calibration
- 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
- 9.1 Joint Torque control
- 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
- 11.1 Kinematic WBC
- 11.2 Dynamic WBC
- 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
- 13.1 WebCommander
- 13.2 Position Control
- 13.3 Walking Controller
- 13.4 Whole Body control
- 13.5 Torque Offset Calibration
- 13.6 Torque Control
- 13.7 Walking Torque Control



# 12 Introspection controller

The introspection controller is used to publish all the statistics and information coming from the sensors, motors and control applications.

By default it's started when launching the DCM controller. Otherwise it needs to be launch as:

```
roslaunch introspection_controller
introspection_controller.launch
```

To record a rosbag:

```
rosbag record /introspection_data/names
/introspection_data/values -o NAME_OF_THE_BAG
```

Copy the rosbag in your development machine and visualize it with **PlotJuggler**:

```
roslaunch plotjuggler PlotJuggler
```



## Quick search



### 1 TALOS Software manual

#### 1.1 GENERAL INFORMATION

##### 2 PAL repositories

##### 3 Gazebo simulation

##### 4 PAL Physics simulator

##### 4.1 Simulation with ideal actuation

##### 4.2 Simulation with gaussian noise

##### 5 Initialization script

##### 6 Position controllers

##### 6.1 Controller manager

##### 6.2 Default controllers

##### 6.3 Full body position controllers

##### 6.4 Play motion

##### 7 Walking controller

##### 7.1 Walking offsets calibration

##### 7.1.1 Load controller

##### 7.1.2 Start calibration

##### 7.1.3 Save the results

##### 8 Torque offset calibration

##### 9 Torque control

##### 9.1 Joint Torque control

##### 9.2 The DCM controller

##### 10 Walking torque control

##### 11 PAL Whole Body Control

##### 11.1 Kinematic WBC

##### 11.2 Dynamic WBC

##### 11.3 WBC grasp demo

##### 12 Introspection controller

##### 13 Validation post upgrade

##### 13.1 WebCommander

##### 13.2 Position Control


##### 13.3 Walking Controller

##### 13.4 Whole Body control

##### 13.5 Torque Offset Calibration

##### 13.6 Torque Control

##### 13.7 Walking Torque Control



### Note

You can create your own layouts in **PlotJuggler**.

Please take a look at the introspection data section of the handbook or at the [pal\\_base\\_ros\\_controller\\_tutorials](#) to understand how to register new variables from your control applications.

## 13 Validation post upgrade

To properly validate the robot after an upgrade, we recommend the user to run the following UAT tests in this specific order:

### 13.1 WebCommander

Open the webcommander of the robot. Check in the diagnostics tab and the startup tab that everything is in green.

### 13.2 Position Control

- First start the initialization script with the robot hanging on air. Wait until the robot says that the initialization finished successfully.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

- Start the default controllers
- Run some motions from the WebCommander:
  - Nod
  - Bow
  - Push Walls
  - Close Both Grippers

## 13.3 Walking Controller

- Copy the *walking\_validation.py* script from the **talos\_uat\_tests** package inside the robot.

```
scp walking_validation.py pal@talos-Xc:
```

- Execute it:

```
python walking_validation.py
```

### Note

The robot will walk in all directions. Wait until the script finishes and the robot has stopped.

## 13.4 Whole Body control

- Copy the *wbc\_validation.py* script from the **talos\_uat\_tests** package inside the robot.

```
scp wbc_validation.py pal@talos-Xc:
```

- Start the Kinematic WBC (before you need to stop the default controllers if they still active):

```
roslaunch talos_wbc talos_wbc.launch
```

- Proceed adding the tasks to control the robot in cartesian space. Open a new terminal connected



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

```
roslaunch talos_wbc_interactive_markers.launch
```

```
source_data:=topic_reflexx_typeII
```

- Execute the script that sends different cartesian poses to each end effector.

```
python wbc_validation.py
```

### Warning

You will need to lower the crane for this experiment.

### Note

Wait until the script has finished and the robot is back to the default position.

## 13.5 Torque Offset Calibration

- Run the torque offset calibration for the **legs** (see it on this manual).
- Check that the computed **offsets** and the **standard deviation** is not high for any sensor.
- Apply the offsets.

Repeat the whole process for the **arms**.

## 13.6 Torque Control

- Put the robot on air and start the initialization script.
- Lower the crane and start the DCM controller.

```
roslaunch talos_pal_locomotion
```

```
robot_dcm_walking_controller.launch
```

- Disturb the robot. It should be compliant.



## Quick search



- 1 TALOS Software manual
- 1.1 GENERAL INFORMATION
- 2 PAL repositories
- 3 Gazebo simulation
- 4 PAL Physics simulator
  - 4.1 Simulation with ideal actuation
  - 4.2 Simulation with gaussian noise
- 5 Initialization script
- 6 Position controllers
  - 6.1 Controller manager
  - 6.2 Default controllers
  - 6.3 Full body position controllers
  - 6.4 Play motion
- 7 Walking controller
  - 7.1 Walking offsets calibration
    - 7.1.1 Load controller
    - 7.1.2 Start calibration
    - 7.1.3 Save the results
- 8 Torque offset calibration
- 9 Torque control
  - 9.1 Joint Torque control
  - 9.2 The DCM controller
- 10 Walking torque control
- 11 PAL Whole Body Control
  - 11.1 Kinematic WBC
  - 11.2 Dynamic WBC
  - 11.3 WBC grasp demo
- 12 Introspection controller
- 13 Validation post upgrade
  - 13.1 WebCommander
  - 13.2 Position Control
  - 13.3 Walking Controller
  - 13.4 Whole Body control
  - 13.5 Torque Offset Calibration
  - 13.6 Torque Control
  - 13.7 Walking Torque Control

- Stop the controller.

## 13.7 Walking Torque Control

- Create a workspace and deploy the `pal_locomotion_tutorials` package inside the robot.

```
roslaunch pal_deploy deploy-py -p
"pal_locomotion_tutorials" talos-Xc
```

- Put the robot on air and start the initialization script.
- Lower the crane and start the DCM controller with fixed upper body.

```
roslaunch talos_pal_locomotion
robot_dcm_walking_controller.launch
robot:=full_v2_fixed_upper_body
```

- Check in RViz that the actual DCM converges to the desired DCM (this is explained in the walking torque control section).
- Execute six steps forward.

```
roslaunch pal_locomotion_tutorials
static_steps_execution_node -d 2.0 -u 2.0 -s 6 -x 0.15
-y 0.1
```

© Copyright 2020, PAL Robotics.

Created using **Sphinx** 3.2.1 with **Press Theme**.